

# Image Server Error Codes

The error numbers and corresponding descriptions listed below are returned in the ImageServerReply XML message in the "CommandErrorCode" attribute of the "ImageServerReply" element.

000	Successful result, No Errors
3	Error reading file
4	Error writing file
11	User generated abort
119	Password is invalid
128	XML parsing error
208	Error opening or reading data file
210	Error reading native file
212	Error creating / opening image file
213	Error sizing image file, i.e. no files or ISO header didn't match
215	Error writing image file
216	Image too large for specified media size
219	Too many subdirectories
220	File already exists in image file
228	File larger than 4.2G for ISO
230	Invalid or not found data source file name
231	Illegal filename for image type
232	Illegal volume name for image type
310	Order does not exist or is no longer active
500	Generic XML error
501	Generic Message Server error

Error Codes returned as 500 or 501 will provide a text response through the "CommandErrorMessage" element of the "ImageServerReply" element which provides more detailed information related to the failure.